

A Traffic Engineering (TE) MIB

Status of This Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Copyright Notice

Copyright (C) The Internet Society (2005).

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, it describes managed objects for Traffic Engineered (TE) Tunnels; for example, Multi-Protocol Label Switched Paths.

Table of Contents

1.	Introduction	2
1.1.	Specification of Requirements.	2
2.	The Internet-Standard Management Framework	2
3.	Overview of the MIB Module	2
3.1.	Traffic Engineering Information.	3
3.2.	Traffic Tunnel Information	3
3.3.	Path Information	3
3.4.	Hop Information.	4
3.5.	Relationship with Other MIB Modules.	4
4.	Creating, Modifying, and Deleting a TE Tunnel.	4
5.	MIB Specification.	5
6.	References	40
6.1.	Normative References	40
6.2.	Informative References	40
7.	Security Considerations.	41
	Acknowledgments.	42
	Author's Address	43
	Full Copyright Statement	44

1. Introduction

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, it describes managed objects for Traffic Engineered (TE) Tunnels; for example, Multi-Protocol Label Switched Paths ([7], [8]). The MIB module defined by this memo allows one to configure TE Tunnels, to assign one or more paths to a Tunnel, and to monitor operational aspects of the Tunnel, such as the number of octets and packets that have passed through the Tunnel.

As it stands, this MIB module can only be used to configure or monitor a TE Tunnel at its ingress. The ingress is then expected to use some protocol (such as RSVP-TE) to signal the other routers in the path the information they need to set up the tunnel. The extension of this module for use at other points of a Tunnel is for further study.

1.1. Specification of Requirements

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in RFC 2119 [1].

2. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to Section 7 of RFC 3410 [8].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIV2, which is described in STD 58, RFC 2578 [2], STD 58, RFC 2579 [3] and STD 58, RFC 2580 [4].

3. Overview of the MIB Module

The Traffic Engineering MIB module consists of four parts:

- 1) Traffic Engineering information,
- 2) a table of Traffic Engineering Tunnels,
- 3) a table of Paths that tunnels take, and
- 4) a table of Hops that make up a tunnel path.

The MIB module also has statements for minimal and full compliance.

The following subsections give an overview of each part. All objects are mandatory. For minimal compliance, all objects MAY be implemented read-only; for full compliance, all objects must be implemented to their stated MAX-ACCESS capabilities. Notifications are optional.

3.1. Traffic Engineering Information

This part contains information about the Link State Protocols used to carry TE information, the signaling protocols used to set up Traffic Tunnels, the number of Traffic Tunnels that have been configured and that are operational, and a mapping of Administrative Group (called Resource Classes in [7]) numbers to names.

3.2. Traffic Tunnel Information

This part contains a table of Traffic Tunnels and information about each one. This information includes the Tunnel name, its configuration information, its operational information, and the active path(s) that the Tunnel takes.

Configuration information includes the end points of the Traffic Tunnel, and the number of configured paths for the Traffic Tunnel.

Operational information includes the current state (up/down), the count of octets and packets sent on the Traffic Tunnel, how long it has been up, and how many state transitions the Traffic Tunnel has had.

Operational path information includes the number of operational paths, the number of path changes, and when the last path change was.

3.3. Path Information

A Tunnel is a logical entity. An instantiation of a Tunnel is one or more Paths; each Path has a route (also called Explicit Route) or sequence of hops. A Path is indexed by a dual index: The primary index is that of the Tunnel to which the Path belongs; the secondary index is that of the Path itself.

The configured information for a Path consists of the constraints for the Path and a configured route.

The operational information consists of the Path status, the computed route (i.e., the route that was computed to satisfy the constraints), and the actual path as recorded by the signaling protocol.

3.4. Hop Information

A path consists of a sequence of hops. A hop can be loose (meaning that the path eventually traverses the specified node) or strict (meaning that the specified node and possibly the link must be the next node in the path). A hop can be specified as an IPv4 address, an IPv6 address, an Autonomous System number or an unnumbered interface index [5].

The Hop Table contains all hops for all paths on a given router. It is organized as follows. There is a primary index that identifies a list of hops and a secondary index that identifies individual hops. Thus, to get the sequence of recorded hops for a path, one looks up the path's `tePathRecordedRoute`, which is a primary index into the Hop Table. Then to get the list of actual hops in order for the recorded path, one uses a secondary index of 1, 2,

3.5. Relationship with Other MIB Modules

A TE Tunnel can extend objects from two other MIB modules; one is the Interfaces MIB [10], and the other is the IP Tunnel MIB [11]. The mechanism for doing so is to assign the TE Tunnel index (`teTunnelIndex`) with a valid `ifIndex` value in `ifTable`.

If a TE Tunnel is deemed an interface, a new interface object is created and assigned an `ifIndex` value in `ifTable`. Then a TE Tunnel object is created, setting `teTunnelIndex` to the same value as the interface index.

If (and only if) a TE Tunnel is considered an interface, it may also be considered an IP tunnel (if the encapsulation of the TE Tunnel is IP). In that case, the interface associated with the TE Tunnel should have its `ifType` set to `tunnel(131)`.

If a TE Tunnel is not considered an interface, then the TE Tunnel index (`teTunnelIndex`) SHOULD be set to a value at least 2^{24} , so that it is distinct from normal interfaces.

4. Creating, Modifying, and Deleting a TE Tunnel

To create a TE Tunnel, one first obtains a free Tunnel index by using the object `teNextTunnelIndex`. One then creates the Tunnel, including all parameters, either as `createAndGo` or `createAndWait`. Then, TE Paths for this Tunnel can be created by using the `teTunnelNextPathIndex` object, again as `createAndGo` or `createAndWait`. A particular Path is computed and signaled when both the Path and the enclosing Tunnel have `RowStatus` 'active'.

To build a Path's configured route, one first gets a free PathHop index by using teNextPathHopIndex, and then builds the route hop-by-hop using the secondary index, setting the AddrType, Address, and HopType for each Hop. Finally, one sets the tePathConfiguredRoute in the Path to the PathHop index obtained.

Modifying certain properties of a TE Tunnel or a TE Path may require setting the RowStatus of the Tunnel (or Path) to 'notInService' before making the changes and then setting the RowStatus of the Tunnel (or Path) back to 'active' to re-signal all Paths of the Tunnel (or the modified Path).

A TE Tunnel and all its Paths can be deleted by setting the Tunnel's RowStatus to 'destroy'. A specific Path within a Tunnel can be destroyed by setting that Path's RowStatus to 'destroy'.

5. MIB Specification

This MIB module IMPORTS objects from RFCs 2578 [2], 2579 [3], 2580 [3], 3411 [6], and 3811 [5] and it also has REFERENCE clauses to RFCs 3209 [8] and 3212 [12].

TE-MIB DEFINITIONS ::= BEGIN

IMPORTS

```

MODULE-IDENTITY, OBJECT-TYPE,
NOTIFICATION-TYPE, mib-2,
Integer32, Gauge32, Counter32,
Counter64, Unsigned32, TimeTicks          FROM SNMPv2-SMI

RowStatus, StorageType, TimeStamp,
TruthValue                                FROM SNMPv2-TC

SnmpAdminString                           FROM SNMP-FRAMEWORK-MIB

MODULE-COMPLIANCE, OBJECT-GROUP,
NOTIFICATION-GROUP                        FROM SNMPv2-CONF

TeHopAddress, TeHopAddressType,
MplsBitRate                               FROM MPLS-TC-STD-MIB;

```

teMIB MODULE-IDENTITY

```

LAST-UPDATED "200501040000Z"              -- 01 January 2005
ORGANIZATION "IETF Traffic Engineering Working Group"
CONTACT-INFO "

```

```

Editor:          Kireeti Kompella
Postal: Juniper Networks, Inc.
               1194 Mathilda Ave

```

Sunnyvale, CA 94089
Tel: +1 408 745 2000
E-mail: kireeti@juniper.net

The IETF Traffic Engineering Working Group is
chaired by Jim Boyle and Ed Kern.

WG Mailing List information:

General Discussion: te-wg@ops.ietf.org
To Subscribe: te-wg-request@ops.ietf.org
In Body: subscribe
Archive: ftp://ops.ietf.org/pub/lists

Comments on the MIB module should be sent to the
mailing list. The archives for this mailing list
should be consulted for previous discussion on
this MIB.

DESCRIPTION "The Traffic Engineering MIB module.

Copyright (C) The Internet Society (2005). This
version of this MIB module is part of RFC 3970;
see the RFC itself for full legal notices.

-- revision history

REVISION "200501040000Z" -- 01 January 2005
DESCRIPTION "Initial version, published as RFC 3970."
::= { mib-2 122 }

-- Top level objects

teMIBNotifications OBJECT IDENTIFIER ::= { teMIB 0 }
teMIBObjects OBJECT IDENTIFIER ::= { teMIB 1 }
teMIBConformance OBJECT IDENTIFIER ::= { teMIB 2 }

-- *****

-- TE MIB Objects

-- TE Info

teInfo OBJECT IDENTIFIER ::= { teMIBObjects 1 }
teDistProtocol OBJECT-TYPE

```

SYNTAX      BITS {
                other(0),
                isis(1),
                ospf(2)
            }
MAX-ACCESS   read-only
STATUS       current
DESCRIPTION  "IGP used to distribute Traffic Engineering
              information and topology to each device for the
              purpose of automatic path computation.  More than
              one IGP may be used to distribute TE information.
              "
 ::= { teInfo 1 }

teSignalingProto OBJECT-TYPE
SYNTAX      BITS {
                other(0),
                rsvpte(1),
                crldp(2),
                static(3)      -- static configuration
            }
MAX-ACCESS   read-only
STATUS       current
DESCRIPTION  "Traffic Engineering signaling protocols supported
              by this device.  More than one protocol may be
              supported.
              "
REFERENCE    "For a description of RSVP-TE, see RFC 3209;
              for CR-LDP, see RFC 3212.
              "
 ::= { teInfo 2 }

teNotificationEnable OBJECT-TYPE
SYNTAX      TruthValue
MAX-ACCESS   read-write
STATUS       current
DESCRIPTION  "If this object is true, then it enables the
              generation of notifications from this MIB module.
              Otherwise notifications are not generated.
              "
DEFVAL      { false }
 ::= { teInfo 3 }

teNextTunnelIndex OBJECT-TYPE
SYNTAX      Unsigned32
MAX-ACCESS   read-only
STATUS       current
DESCRIPTION  "An integer that may be used as a new Index in the

```

teTunnelTable.

The special value of 0 indicates that no more new entries can be created in that table.

When this MIB module is used for configuration, this object always contains a legal value (if non-zero) for an index that is not currently used in that table. The Command Generator (Network Management Application) reads this variable and uses the (non-zero) value read when creating a new row with an SNMP SET. When the SET is performed, the Command Responder (agent) must determine whether the value is indeed still unused; Two Network Management Applications may attempt to create a row (configuration entry) simultaneously and use the same value. If it is currently unused, the SET succeeds, and the Command Responder (agent) changes the value of this object according to an implementation-specific algorithm. If the value is in use, however, the SET fails. The Network Management Application must then re-read this variable to obtain a new usable value.

::= { teInfo 4 }

teNextPathHopIndex OBJECT-TYPE

SYNTAX Unsigned32

MAX-ACCESS read-only

STATUS current

DESCRIPTION "An integer that may be used as a new Index in the tePathHopTable.

The special value of 0 indicates that no more new entries can be created in that table.

When this MIB module is used for configuration, this object always contains a legal value (if non-zero) for an index that is not currently used in that table. The Command Generator (Network Management Application) reads this variable and uses the (non-zero) value read when creating a new row with an SNMP SET. When the SET is performed, the Command Responder (agent) must determine whether the value is indeed still unused; Two Network Management Applications may attempt to create a row (configuration entry) simultaneously and use the same value. If it is currently unused, the SET

succeeds, and the Command Responder (agent) changes the value of this object according to an implementation-specific algorithm. If the value is in use, however, the SET fails. The Network Management Application must then re-read this variable to obtain a new usable value.

```
"
 ::= { teInfo 5 }

teConfiguredTunnels OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "Number of currently configured Tunnels."
    ::= { teInfo 6 }

teActiveTunnels OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "Number of currently active Tunnels."
    ::= { teInfo 7 }

tePrimaryTunnels OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "Number of currently active Tunnels running on
                their primary paths."
    ::= { teInfo 8 }

teAdminGroupTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF TeAdminGroupEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION "A mapping of configured administrative groups. Each
                entry represents an Administrative Group and
                provides a name and index for the group.
                Administrative groups are used to label links in the
                Traffic Engineering topology in order to place
                constraints (include and exclude) on Tunnel paths.

                A groupName can only be linked to one group number.
                The groupName is the number assigned to the
                administrative group used in constraints,
                such as tePathIncludeAny or tePathIncludeAll."
    ::= { teInfo 9 }
```

```
::= { teInfo 9 }
```

```
teAdminGroupEntry OBJECT-TYPE
    SYNTAX      TeAdminGroupEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION "A mapping between a configured group number and
                its human-readable name. The group number should
                be between 1 and 32, inclusive. Group number n
                represents bit number (n-1) in the bit vector for
                Include/Exclude constraints.

                All entries in this table MUST be kept in stable
                storage so that they will re-appear in case of a
                restart/reboot.

                "
    INDEX       { teAdminGroupNumber }
    ::= { teAdminGroupTable 1 }
```

```
TeAdminGroupEntry ::=
    SEQUENCE {
        teAdminGroupNumber      Integer32,
        teAdminGroupName        SnmpAdminString,
        teAdminGroupRowStatus   RowStatus
    }
```

```
teAdminGroupNumber OBJECT-TYPE
    SYNTAX      Integer32 (1..32)
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION "Index of the administrative group."
    ::= { teAdminGroupEntry 1 }
```

```
teAdminGroupName OBJECT-TYPE
    SYNTAX      SnmpAdminString (SIZE (1..32))
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "Name of the administrative group."
    ::= { teAdminGroupEntry 2 }
```

```
teAdminGroupRowStatus OBJECT-TYPE
    SYNTAX      RowStatus
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "The status of this conceptual row.
```

The value of this object has no effect on whether other objects in this conceptual row can be

```

        modified.
    "
    ::= { teAdminGroupEntry 3 }

-- Tunnel Table

teTunnelTable      OBJECT-TYPE
    SYNTAX          SEQUENCE OF TeTunnelEntry
    MAX-ACCESS      not-accessible
    STATUS          current
    DESCRIPTION     "Table of Configured Traffic Tunnels."
    ::= { teMIBObjects 2 }

teTunnelEntry      OBJECT-TYPE
    SYNTAX          TeTunnelEntry
    MAX-ACCESS      not-accessible
    STATUS          current
    DESCRIPTION     "Entry containing information about a particular
                    Traffic Tunnel."
    "
    INDEX           { teTunnelIndex }
    ::= { teTunnelTable 1 }

TeTunnelEntry ::=
    SEQUENCE {
        teTunnelIndex          Unsigned32,
        teTunnelName           SnmAdminString,
        teTunnelNextPathIndex  Unsigned32,
        -- Conceptual row information:
        teTunnelRowStatus      RowStatus,
        teTunnelStorageType    StorageType,
        -- Address information:
        teTunnelSourceAddressType  TeHopAddressType,
        teTunnelSourceAddress      TeHopAddress,
        teTunnelDestinationAddressType TeHopAddressType,
        teTunnelDestinationAddress TeHopAddress,
        -- State/performance information:
        teTunnelState           INTEGER,
        teTunnelDiscontinuityTimer  TimeStamp,
        teTunnelOctets          Counter64,
        teTunnelPackets         Counter64,
        teTunnelLPOctets        Counter32,
        teTunnelLPPackets        Counter32,
        teTunnelAge              TimeTicks,
        teTunnelTimeUp           TimeTicks,
        teTunnelPrimaryTimeUp     TimeTicks,
        teTunnelTransitions      Counter32,
        teTunnelLastTransition    TimeTicks,
    }

```

```

        teTunnelPathChanges          Counter32,
        teTunnelLastPathChange       TimeTicks,
        teTunnelConfiguredPaths      Gauge32,
        teTunnelStandbyPaths         Gauge32,
        teTunnelOperationalPaths     Gauge32
    }

teTunnelIndex OBJECT-TYPE
    SYNTAX      Unsigned32 (1..4294967295)
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION "A unique index that identifies a Tunnel.  If the TE
                Tunnel is considered an interface, then this index
                must match the interface index of the corresponding
                interface.  Otherwise, this index must be at least
                2^24, so that it does not overlap with any existing
                interface index.
                "
    ::= { teTunnelEntry 1 }

teTunnelName OBJECT-TYPE
    SYNTAX      SnmpAdminString (SIZE (1..32))
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "Name of the Traffic Tunnel.

                Note that the name of a Tunnel MUST be unique.
                When a SET request contains a name that is already
                in use for another entry, then the implementation
                must return an inconsistentValue error.

                The value of this object cannot be changed if the
                if the value of the corresponding teTunnelRowStatus
                object is 'active'.
                "
    ::= { teTunnelEntry 2 }

teTunnelNextPathIndex OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "An integer that may be used as a new Index for the
                next Path in this Tunnel.

                The special value of 0 indicates that no more Paths
                can be created for this Tunnel, or that no more new
                entries can be created in tePathTable.
    
```

When this MIB module is used for configuration, this object always contains a legal value (if non-zero) for an index that is not currently used in that table. The Command Generator (Network Management Application) reads this variable and uses the (non-zero) value read when creating a new row with an SNMP SET. When the SET is performed, the Command Responder (agent) must determine whether the value is indeed still unused; Two Network Management Applications may attempt to create a row (configuration entry) simultaneously and use the same value. If it is currently unused, the SET succeeds, and the Command Responder (agent) changes the value of this object according to an implementation-specific algorithm. If the value is in use, however, the SET fails. The Network Management Application must then re-read this variable to obtain a new usable value.

```
"
 ::= { teTunnelEntry 3 }
```

teTunnelRowStatus OBJECT-TYPE

```
SYNTAX      RowStatus
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION "The status of this conceptual row.
```

When the value of this object is 'active', then the values for the corresponding objects teTunnelName, teTunnelSourceAddressType, teTunnelSourceAddress, teTunnelDestinationAddressType, and teTunnelDestinationAddress cannot be changed.

```
"
 ::= { teTunnelEntry 4 }
```

teTunnelStorageType OBJECT-TYPE

```
SYNTAX      StorageType
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION "The storage type for this conceptual row.
```

Conceptual rows having the value 'permanent' need not allow write-access to any columnar objects in the row.

```
"
 ::= { teTunnelEntry 5 }
```

```
teTunnelSourceAddressType OBJECT-TYPE
    SYNTAX      TeHopAddressType
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "The type of Traffic Engineered Tunnel hop address
                for the source of this Tunnel. Typically, this
                address type is IPv4 or IPv6, with a prefix length
                of 32 or 128, respectively. If the TE Tunnel path
                is being computed by a path computation server,
                however, it is possible to use more flexible source
                address types, such as AS numbers or prefix lengths
                less than host address lengths.

                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'."
    ::= { teTunnelEntry 6 }

teTunnelSourceAddress OBJECT-TYPE
    SYNTAX      TeHopAddress
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "The Source Traffic Engineered Tunnel hop address of
                this Tunnel.

                The type of this address is determined by the value
                of the corresponding teTunnelSourceAddressType.

                Note that the source and destination addresses of a
                Tunnel can be different address types.

                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'."
    ::= { teTunnelEntry 7 }

teTunnelDestinationAddressType OBJECT-TYPE
    SYNTAX      TeHopAddressType
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "The type of Traffic Engineered Tunnel hop address
                for the destination of this Tunnel.

                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'."
```

```

"
 ::= { teTunnelEntry 8 }

teTunnelDestinationAddress OBJECT-TYPE
    SYNTAX      TeHopAddress
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "The Destination Traffic Engineered Tunnel hop
                address of this Tunnel.

                The type of this address is determined by the value
                of the corresponding teTunnelDestinationAddressType.

                Note that source and destination addresses of a
                Tunnel can be different address types.

                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'."
"
 ::= { teTunnelEntry 9 }

teTunnelState OBJECT-TYPE
    SYNTAX      INTEGER {
                unknown(1),
                up(2),
                down(3),
                testing(4)
                }
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The operational state of the Tunnel."
 ::= { teTunnelEntry 10 }

teTunnelDiscontinuityTimer OBJECT-TYPE
    SYNTAX      TimeStamp
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The value of sysUpTime on the most recent occasion
                at which any one or more of this tunnel's counters
                suffered a discontinuity. The relevant counters
                are teTunnelOctets, teTunnelPackets,
                teTunnelLPOctets, and teTunnelLPPackets. If no such
                discontinuities have occurred since the last
                re-initialization of the local management subsystem
                then this object contains a zero value."
"
 ::= { teTunnelEntry 11 }

```

```

teTunnelOctets OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION "The number of octets that have been forwarded over
                the Tunnel.

                Discontinuities in the value of this counter can
                occur at re-initialization of the management system,
                and at other times, as indicated by the value of
                teTunnelDiscontinuityTimer.
                "
    ::= { teTunnelEntry 12 }

teTunnelPackets OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION "The number of packets that have been forwarded over
                the Tunnel.

                Discontinuities in the value of this counter can
                occur at re-initialization of the management system
                and at other times, as indicated by the value of
                teTunnelDiscontinuityTimer.
                "
    ::= { teTunnelEntry 13 }

teTunnelLPOctets OBJECT-TYPE
    SYNTAX Counter32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION "The number of octets that have been forwarded over
                the Tunnel.

                Discontinuities in the value of this counter can
                occur at re-initialization of the management system
                and at other times, as indicated by the value of
                teTunnelDiscontinuityTimer.
                "
    ::= { teTunnelEntry 14 }

teTunnelLPPackets OBJECT-TYPE
    SYNTAX Counter32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION "The number of packets that have been forwarded over
                the Tunnel.

```


Discontinuities in the value of this counter can occur at re-initialization of the management system and at other times, as indicated by the value of teTunnelDiscontinuityTimer.

```

"
 ::= { teTunnelEntry 15 }

teTunnelAge      OBJECT-TYPE
SYNTAX          TimeTicks
MAX-ACCESS      read-only
STATUS          current
DESCRIPTION     "The age (i.e., time from creation of this conceptual
                 row till now) of this Tunnel in hundredths of a
                 second. Note that because TimeTicks wrap in about
                 16 months, this value is best used in interval
                 measurements.
"
 ::= { teTunnelEntry 16 }

teTunnelTimeUp   OBJECT-TYPE
SYNTAX          TimeTicks
MAX-ACCESS      read-only
STATUS          current
DESCRIPTION     "The total time in hundredths of a second that this
                 Tunnel has been operational. Note that because
                 TimeTicks wrap in about 16 months, this value is
                 best used in interval measurements.

                 An example of usage of this object would be to
                 compute the percentage up time over a period of time
                 by obtaining values of teTunnelAge and
                 teTunnelTimeUp at two points in time and computing
                 the following ratio:
                 ((teTunnelTimeUp2 - teTunnelTimeUp1)/
                 (teTunnelAge2 - teTunnelAge1)) * 100 %. In doing
                 so, the management station must account for
                 wrapping of the values of teTunnelAge and
                 teTunnelTimeUp between the two measurements.
"
 ::= { teTunnelEntry 17 }

teTunnelPrimaryTimeUp OBJECT-TYPE
SYNTAX          TimeTicks
MAX-ACCESS      read-only
STATUS          current
DESCRIPTION     "The total time in hundredths of a second that this
                 Tunnel's primary path has been operational. Note
                 that because TimeTicks wrap in about 16 months, this

```

value is best used in interval measurements.

An example of usage of this field would be to compute what percentage of time that a TE Tunnel was on the primary path over a period of time by computing $((\text{teTunnelPrimaryTimeUp2} - \text{teTunnelPrimaryTimeUp1}) / (\text{teTunnelTimeUp2} - \text{teTunnelTimeUp1})) * 100 \%$. In doing so, the management station must account for wrapping of the values of `teTunnelPrimaryTimeUp` and `teTunnelTimeUp` between the two measurements.

```

"
 ::= { teTunnelEntry 18 }

teTunnelTransitions OBJECT-TYPE
    SYNTAX      Counter32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The number of operational state transitions
                (up -> down and down -> up) this Tunnel has
                undergone.
"
 ::= { teTunnelEntry 19 }

teTunnelLastTransition OBJECT-TYPE
    SYNTAX      TimeTicks
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The time in hundredths of a second since the last
                operational state transition occurred on this
                Tunnel.

                Note that if the last transition was over 16
                months ago, this value will be inaccurate.
"
 ::= { teTunnelEntry 20 }

teTunnelPathChanges OBJECT-TYPE
    SYNTAX      Counter32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The number of path changes this Tunnel has had."
 ::= { teTunnelEntry 21 }

teTunnelLastPathChange OBJECT-TYPE
    SYNTAX      TimeTicks
    MAX-ACCESS  read-only
    STATUS      current

```

```

DESCRIPTION "The time in hundredths of a second since the last
             path change occurred on this Tunnel.

             Note that if the last transition was over 16
             months ago, this value will be inaccurate.

             Path changes may be caused by network events or by
             reconfiguration that affects the path.
             "
 ::= { teTunnelEntry 22 }

teTunnelConfiguredPaths OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The number of paths configured for this Tunnel."
    ::= { teTunnelEntry 23 }

teTunnelStandbyPaths OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The number of standby paths configured for this
                Tunnel.
                "
    ::= { teTunnelEntry 24 }

teTunnelOperationalPaths OBJECT-TYPE
    SYNTAX      Gauge32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The number of operational paths for this Tunnel.
                This includes the path currently active, as
                well as operational standby paths.
                "
    ::= { teTunnelEntry 25 }

-- *****
--
-- Tunnel Path Table
--

tePathTable      OBJECT-TYPE
    SYNTAX      SEQUENCE OF TePathEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION "Table of Configured Traffic Tunnels."
    ::= { teMIBObjects 3 }

```

```

tePathEntry      OBJECT-TYPE
  SYNTAX          TePathEntry
  MAX-ACCESS      not-accessible
  STATUS          current
  DESCRIPTION    "Entry containing information about a particular
                  Traffic Tunnel.  Each Traffic Tunnel can have zero
                  or more Traffic Paths.

                  As a Traffic Path can only exist over an existing
                  Traffic Tunnel, all tePathEntries with
                  a value of n for teTunnelIndex MUST be removed by
                  the implementation when the corresponding
                  teTunnelEntry with a value of n for teTunnelIndex
                  is removed.

                  "
  INDEX           { teTunnelIndex, tePathIndex }
  ::= { tePathTable 1 }

TePathEntry ::=
  SEQUENCE {
    tePathIndex          Unsigned32,
    tePathName           SnmpAdminString,
    -- Conceptual row information
    tePathRowStatus      RowStatus,
    tePathStorageType    StorageType,
    -- Path properties
    tePathType           INTEGER,
    tePathConfiguredRoute Unsigned32,
    tePathBandwidth      MplsBitRate,
    tePathIncludeAny     Unsigned32,
    tePathIncludeAll     Unsigned32,
    tePathExclude        Unsigned32,
    tePathSetupPriority  Integer32,
    tePathHoldPriority   Integer32,
    tePathProperties     BITS,
    -- Path status
    tePathOperStatus     INTEGER,
    tePathAdminStatus    INTEGER,
    tePathComputedRoute  Unsigned32,
    tePathRecordedRoute  Unsigned32
  }

tePathIndex      OBJECT-TYPE
  SYNTAX          Unsigned32 (1..4294967295)
  MAX-ACCESS      not-accessible
  STATUS          current
  DESCRIPTION    "An index that uniquely identifies a path within
                  a Tunnel.

```

The combination of <teTunnelIndex, tePathIndex> thus uniquely identifies a path among all paths on this router.

"

::= { tePathEntry 1 }

tePathName OBJECT-TYPE
 SYNTAX SnmpAdminString (SIZE(0..32))
 MAX-ACCESS read-create
 STATUS current
 DESCRIPTION "The name of this path.

A pathName must be unique within the set of paths over a single tunnel. If a SET request is received with a duplicate name, then the implementation MUST return an inconsistentValue error.

The value of this object cannot be changed if the value of the corresponding teTunnelRowStatus object is 'active'.

"

::= { tePathEntry 2 }

tePathRowStatus OBJECT-TYPE
 SYNTAX RowStatus
 MAX-ACCESS read-create
 STATUS current
 DESCRIPTION "The status of this conceptual row.

When the value of this object is 'active', then the value of tePathName cannot be changed. All other writable objects may be changed; however, these changes may affect traffic going over the TE tunnel or require the path to be computed and/or re-signaled.

"

::= { tePathEntry 3 }

tePathStorageType OBJECT-TYPE
 SYNTAX StorageType
 MAX-ACCESS read-create
 STATUS current
 DESCRIPTION "The storage type for this conceptual row.

Conceptual rows having the value 'permanent' need not allow write-access to any columnar objects in the row.

"

```

 ::= { tePathEntry 4 }

tePathType OBJECT-TYPE
    SYNTAX      INTEGER {
                other(1),
                primary(2),
                standby(3),
                secondary(4)
                }
    MAX-ACCESS   read-create
    STATUS       current
    DESCRIPTION  "The type for this PathEntry; i.e., whether this path
                 is a primary path, a standby path, or a secondary
                 path."
 ::= { tePathEntry 5 }

tePathConfiguredRoute OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS   read-create
    STATUS       current
    DESCRIPTION  "The route that this TE path is configured to follow;
                 i.e., an ordered list of hops. The value of this
                 object gives the primary index into the Hop Table.
                 The secondary index is the hop count in the path, so
                 to get the route, one could get the first hop with
                 index <tePathConfiguredRoute, 1> in the Hop Table
                 and do a getnext to get subsequent hops."
 ::= { tePathEntry 6 }

tePathBandwidth OBJECT-TYPE
    SYNTAX      MplsBitRate
    UNITS        "Kilobits per second"
    MAX-ACCESS   read-create
    STATUS       current
    DESCRIPTION  "The configured bandwidth for this Tunnel,
                 in units of thousands of bits per second (Kbps)."
    DEFVAL      { 0 }
 ::= { tePathEntry 7 }

tePathIncludeAny OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS   read-create
    STATUS       current
    DESCRIPTION  "This is a configured set of administrative groups
                 specified as a bit vector (i.e., bit n is 1 if group

```

n is in the set, where n = 0 is the LSB). For each link that this path goes through, the link must have at least one of the groups specified in IncludeAny to be acceptable. If IncludeAny is zero, all links are acceptable.

```
"
DEFVAL      { 0 }
::= { tePathEntry 8 }
```

tePathIncludeAll OBJECT-TYPE

```
SYNTAX      Unsigned32
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION "This is a configured set of administrative groups
            specified as a bit vector (i.e., bit n is 1 if group
            n is in the set, where n = 0 is the LSB). For each
            link that this path goes through, the link must have
            all of the groups specified in IncludeAll to be
            acceptable. If IncludeAll is zero, all links are
            acceptable.
            "
DEFVAL      { 0 }
::= { tePathEntry 9 }
```

tePathExclude OBJECT-TYPE

```
SYNTAX      Unsigned32
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION "This is a configured set of administrative groups
            specified as a bit vector (i.e., bit n is 1 if group
            n is in the set, where n = 0 is the LSB). For each
            link that this path goes through, the link MUST have
            groups associated with it, and the intersection of
            the link's groups and the 'exclude' set MUST be
            null.
            "
DEFVAL      { 0 }
::= { tePathEntry 10 }
```

tePathSetupPriority OBJECT-TYPE

```
SYNTAX      Integer32 (0..7)
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION "The setup priority configured for this path, with 0
            as the highest priority and 7 as the lowest.
            "
DEFVAL      { 7 }
```

```

 ::= { tePathEntry 11 }

tePathHoldPriority OBJECT-TYPE
    SYNTAX      Integer32 (0..7)
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "The hold priority configured for this path, with 0
                as the highest priority and 7 as the lowest.
                "
    DEFVAL      { 0 }
 ::= { tePathEntry 12 }

tePathProperties OBJECT-TYPE
    SYNTAX      BITS {
                recordRoute(0),
                cspf(1),
                makeBeforeBreak(2),
                mergeable(3),
                fastReroute(4),
                protected(5)
                }
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "The set of configured properties for this path,
                expressed as a bit map.  For example, if the path
                supports 'make before break', then bit 2 is set.
                "
 ::= { tePathEntry 13 }

tePathOperStatus OBJECT-TYPE
    SYNTAX      INTEGER {
                unknown(0),
                down(1),
                testing(2),
                dormant(3),
                ready(4),
                operational(5)
                }
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The operational status of the path:
                unknown:
                down:      Signaling failed.
                testing:   Administratively set aside for testing.
                dormant:   Not signaled (for a backup tunnel).
                ready:     Signaled but not yet carrying traffic.
                operational: Signaled and carrying traffic.
                "

```



```
 ::= { tePathEntry 14 }

tePathAdminStatus OBJECT-TYPE
    SYNTAX      INTEGER {
                    normal(1),
                    testing(2)
                }
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "The operational status of the path:
                normal:      Used normally for forwarding.
                testing:    Administratively set aside for testing.
                "
 ::= { tePathEntry 15 }

tePathComputedRoute OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The route computed for this path, perhaps using
                some form of Constraint-based Routing. The
                algorithm is implementation dependent.

                This object returns the computed route as an ordered
                list of hops. The value of this object gives the
                primary index into the Hop Table. The secondary
                index is the hop count in the path, so to get the
                route, one could get the first hop with index
                <tePathComputedRoute, 1> in the Hop Table and do a
                getnext to get subsequent hops.

                A value of zero (0) means there is no computedRoute.
                "
 ::= { tePathEntry 16 }

tePathRecordedRoute OBJECT-TYPE
    SYNTAX      Unsigned32
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The route actually used for this path, as recorded
                by the signaling protocol. This is again an ordered
                list of hops; each hop is expected to be strict.

                The value of this object gives the primary index
                into the Hop Table. The secondary index is the hop
                count in the path, so to get the route, one can get
                the first hop with index <tePathRecordedRoute, 1>
                in the Hop Table and do a getnext to get subsequent
```

```

        hops.

        A value of zero (0) means there is no recordedRoute.
        "
 ::= { tePathEntry 17 }

-- *****
--
-- Tunnel Path Hop Table
--

tePathHopTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF TePathHopEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION "Table of Tunnel Path Hops."
    ::= { teMIBObjects 4 }

tePathHopEntry OBJECT-TYPE
    SYNTAX      TePathHopEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION "Entry containing information about a particular
                hop.
                "
    INDEX       { teHopListIndex, tePathHopIndex }
    ::= { tePathHopTable 1 }

TePathHopEntry ::=
    SEQUENCE {
        teHopListIndex      Unsigned32,
        tePathHopIndex      Unsigned32,
        -- Conceptual row information
        tePathHopRowStatus  RowStatus,
        tePathHopStorageType StorageType,
        tePathHopAddrType   TeHopAddressType,
        tePathHopAddress     TeHopAddress,
        tePathHopType       INTEGER
    }

teHopListIndex OBJECT-TYPE
    SYNTAX      Unsigned32 (1..4294967295)
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION "An index that identifies a list of hops. This is
                the primary index to access hops.
                "
    ::= { tePathHopEntry 1 }

```

```
tePathHopIndex OBJECT-TYPE
  SYNTAX      Unsigned32 (1..4294967295)
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION "An index that identifies a particular hop among the
              list of hops for a path. An index of i identifies
              the ith hop. This is the secondary index for a hop
              entry.
              "
  ::= { tePathHopEntry 2 }

tePathHopRowStatus OBJECT-TYPE
  SYNTAX      RowStatus
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION "The status of this conceptual row.

              Any field in this table can be changed, even if the
              value of this object is 'active'. However, such a
              change may cause traffic to be rerouted or even
              disrupted.
              "
  ::= { tePathHopEntry 3 }

tePathHopStorageType OBJECT-TYPE
  SYNTAX      StorageType
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION "The storage type for this conceptual row.

              Conceptual rows having the value 'permanent' need
              not allow write-access to any columnar objects
              in the row.
              "
  ::= { tePathHopEntry 4 }

tePathHopAddrType OBJECT-TYPE
  SYNTAX      TeHopAddressType
  MAX-ACCESS  read-create
  STATUS      current
  DESCRIPTION "The type of Traffic Engineered Tunnel hop Address
              of this hop.

              The value of this object cannot be changed
              if the value of the corresponding tePathRowStatus
              object is 'active'.
              "
  ::= { tePathHopEntry 5 }
```

```

tePathHopAddress OBJECT-TYPE
    SYNTAX      TeHopAddress
    MAX-ACCESS  read-create
    STATUS      current
    DESCRIPTION "The Traffic Engineered Tunnel hop Address of this
                hop.

                The type of this address is determined by the value
                of the corresponding tePathHopAddressType.

                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'."
    ::= { tePathHopEntry 6 }

tePathHopType OBJECT-TYPE
    SYNTAX      INTEGER {
                unknown(0),
                loose(1),
                strict(2)
                }
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION "The type of hop:
                unknown:
                loose:   This hop is a LOOSE hop.
                strict:  This hop is a STRICT hop."
    ::= { tePathHopEntry 7 }

-- *****
--
-- TE Notifications
--

teTunnelUp NOTIFICATION-TYPE
    OBJECTS    { teTunnelName,
                tePathName } -- TunnelPath
    STATUS      current
    DESCRIPTION "A teTunnelUp notification is generated when the
                Tunnel indexed by teTunnelName transitions to the
                'up' state.

                A tunnel is up when at least one of its paths is up.
                The tePathName is the name of the path whose
                transition to up made the tunnel go up."

```

This notification MUST be limited to at most one every minute, in case the tunnel flaps up and down.

"

::= { teMIBNotifications 1 }

teTunnelDown NOTIFICATION-TYPE
 OBJECTS { teTunnelName,
 tePathName } -- TunnelPath
 STATUS current
 DESCRIPTION "A teTunnelDown notification is generated when the Tunnel indexed by teTunnelName transitions to the 'down' state.

A tunnel is up when at least one of its paths is up. The tePathName is the name of the path whose transition to down made the tunnel go down.

This notification MUST be limited to at most one every minute, in case the tunnel flaps up and down.

"

::= { teMIBNotifications 2 }

teTunnelChanged NOTIFICATION-TYPE
 OBJECTS { teTunnelName,
 tePathName } -- toTunnelPath
 STATUS current
 DESCRIPTION "A teTunnelChanged notification is generated when an active path on the Tunnel indexed by teTunnelName changes or a new path becomes active. The value of tePathName is the new active path.

This notification MUST be limited to at most one every minute, in case the tunnel changes quickly.

"

::= { teMIBNotifications 3 }

teTunnelRerouted NOTIFICATION-TYPE
 OBJECTS { teTunnelName,
 tePathName } -- toTunnelPath
 STATUS current
 DESCRIPTION "A teTunnelRerouted notification is generated when an active path for the Tunnel indexed by teTunnelName stays the same, but its route changes.

This notification MUST be limited to at most one every minute, in case the tunnel reroutes quickly.

"

::= { teMIBNotifications 4 }

```
-- End of TE-MIB objects

-- *****
--
-- TE Compliance Statements
--

teGroups
    OBJECT IDENTIFIER ::= { teMIBConformance 1 }

teModuleCompliance
    OBJECT IDENTIFIER ::= { teMIBConformance 2 }

-- *****
--
-- TE object groups
--

teTrafficEngineeringGroup OBJECT-GROUP
    OBJECTS {
        teTunnelName,
        teTunnelNextPathIndex,
        teTunnelRowStatus,
        teTunnelStorageType,
        teTunnelSourceAddressType,
        teTunnelSourceAddress,
        teTunnelDestinationAddressType,
        teTunnelDestinationAddress,
        teTunnelState,
        teTunnelDiscontinuityTimer,
        teTunnelOctets,
        teTunnelPackets,
        teTunnelLPOctets,
        teTunnelLPPackets,
        teTunnelAge,
        teTunnelTimeUp,
        teTunnelPrimaryTimeUp,
        teTunnelTransitions,
        teTunnelLastTransition,
        teTunnelPathChanges,
        teTunnelLastPathChange,
        teTunnelConfiguredPaths,
        teTunnelStandbyPaths,
        teTunnelOperationalPaths,
        tePathBandwidth,
        tePathIncludeAny,
        tePathIncludeAll,
        tePathExclude,
```

```
    tePathSetupPriority,
    tePathHoldPriority,
    tePathProperties,
    tePathOperStatus,
    tePathAdminStatus,
    tePathComputedRoute,
    tePathRecordedRoute,
    teDistProtocol,
    teSignalingProto,
    teNotificationEnable,
    teNextTunnelIndex,
    teNextPathHopIndex,
    teAdminGroupName,
    teAdminGroupRowStatus,
    teConfiguredTunnels,
    teActiveTunnels,
    tePrimaryTunnels,
    tePathName,
    tePathType,
    tePathRowStatus,
    tePathStorageType,
    tePathConfiguredRoute,
    tePathHopRowStatus,
    tePathHopStorageType,
    tePathHopAddrType,
    tePathHopAddress,
    tePathHopType
}
STATUS          current
DESCRIPTION "Objects for Traffic Engineering in this MIB module."
 ::= { teGroups 1 }

teNotificationGroup NOTIFICATION-GROUP
NOTIFICATIONS {
    teTunnelUp,
    teTunnelDown,
    teTunnelChanged,
    teTunnelRerouted
}
STATUS          current
DESCRIPTION "Notifications specified in this MIB module."
 ::= { teGroups 2 }

-- *****
--
-- TE compliance statements
--
--   There are four compliance statements: read-only and full
```

```
-- compliance for regular TE devices, and read-only and full
-- compliance for path computation servers.
--
```

```
teModuleReadOnlyCompliance MODULE-COMPLIANCE
```

```
STATUS current
DESCRIPTION "When this MIB module is implemented without support
for read-create (i.e., in read-only mode), then such
an implementation can claim read-only compliance.
Such a device can be monitored but cannot be
configured with this MIB module.
"
```

```
MODULE -- enclosing module, i.e., TE-MIB
```

```
MANDATORY-GROUPS {
    teTrafficEngineeringGroup
}
```

```
GROUP teNotificationGroup
DESCRIPTION "Implementation of this group is optional."
```

```
OBJECT teNotificationEnable
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
```

```
OBJECT teAdminGroupName
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
```

```
OBJECT teAdminGroupRowStatus
SYNTAX RowStatus { active(1) }
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
```

```
OBJECT teTunnelName
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
```

```
OBJECT teTunnelRowStatus
SYNTAX RowStatus { active(1) }
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
```

```
OBJECT teTunnelStorageType
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
```


OBJECT teTunnelSourceAddressType
SYNTAX TeHopAddressType { ipv4(1), ipv6(2) }
MIN-ACCESS read-only
DESCRIPTION "Write access is not required. An
 implementation is only required to support
 IPv4 and IPv6 host addresses."

OBJECT teTunnelSourceAddress
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

OBJECT teTunnelDestinationAddressType
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

OBJECT teTunnelDestinationAddress
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

OBJECT tePathName
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

OBJECT tePathRowStatus
SYNTAX RowStatus { active(1) }
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

OBJECT tePathStorageType
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

OBJECT tePathType
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

OBJECT tePathConfiguredRoute
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

OBJECT tePathBandwidth
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

OBJECT tePathIncludeAny
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."

```

OBJECT      tePathIncludeAll
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathExclude
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathSetupPriority
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHoldPriority
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathProperties
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathAdminStatus
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHopRowStatus
SYNTAX      RowStatus { active(1) }
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHopStorageType
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHopAddrType
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHopAddress
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

```

```
 ::= { teModuleCompliance 1 }
```

```

teModuleFullCompliance MODULE-COMPLIANCE
STATUS      current
DESCRIPTION "When this MIB module is implemented with support for
read-create, then the implementation can claim
full compliance. Such devices can be both

```

monitored and configured with this MIB module.

"

```
MODULE      -- enclosing module, i.e., TE-MIB

MANDATORY-GROUPS {
    teTrafficEngineeringGroup
}

GROUP      teNotificationGroup
DESCRIPTION "Implementation of this group is optional."

OBJECT     teAdminGroupRowStatus
SYNTAX     RowStatus { active(1) }
WRITE-SYNTAX RowStatus { createAndGo(4), destroy(6) }
DESCRIPTION "Support for notInService, createAndWait and
            notReady is not required.
            "

OBJECT     teTunnelRowStatus
SYNTAX     RowStatus { active(1), notInService(2) }
WRITE-SYNTAX RowStatus { active(1), notInService(2),
                        createAndGo(4), destroy(6)
                        }
DESCRIPTION "Support for createAndWait and notReady is not
            required.
            "

OBJECT     teTunnelSourceAddressType
SYNTAX     TeHopAddressType { ipv4(1), ipv6(2) }
DESCRIPTION "Write access is required. An implementation is
            only required to support IPv4 and IPv6 host
            addresses.
            "

OBJECT     tePathRowStatus
SYNTAX     RowStatus { active(1), notInService(2) }
WRITE-SYNTAX RowStatus { active(1), notInService(2),
                        createAndGo(4), destroy(6)
                        }
DESCRIPTION "Support for createAndWait and notReady is not
            required.
            "

OBJECT     tePathHopRowStatus
SYNTAX     RowStatus { active(1), notInService(2) }
WRITE-SYNTAX RowStatus { active(1), notInService(2),
```

```

                                createAndGo(4), destroy(6)
                                }
    DESCRIPTION "Support for createAndWait and notReady is not
                required.
                "
 ::= { teModuleCompliance 2 }

teModuleServerReadOnlyCompliance MODULE-COMPLIANCE
    STATUS          current
    DESCRIPTION "When this MIB module is implemented by a path
                computation server without support for read-create
                (i.e., in read-only mode), then the implementation
                can claim read-only compliance. Such
                a device can be monitored but cannot be
                configured with this MIB module.
                "

MODULE             -- enclosing module, i.e., TE-MIB

    MANDATORY-GROUPS {
        teTrafficEngineeringGroup
    }

    GROUP           teNotificationGroup
    DESCRIPTION "Implementation of this group is optional."

    OBJECT          teNotificationEnable
    MIN-ACCESS      read-only
    DESCRIPTION "Write access is not required."

    OBJECT          teAdminGroupName
    MIN-ACCESS      read-only
    DESCRIPTION "Write access is not required."

    OBJECT          teAdminGroupRowStatus
    SYNTAX          RowStatus { active(1) }
    MIN-ACCESS      read-only
    DESCRIPTION "Write access is not required."

    OBJECT          teTunnelName
    MIN-ACCESS      read-only
    DESCRIPTION "Write access is not required."

    OBJECT          teTunnelRowStatus
    SYNTAX          RowStatus { active(1) }
    MIN-ACCESS      read-only
    DESCRIPTION "Write access is not required."

```

```
OBJECT      teTunnelStorageType
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      teTunnelSourceAddressType
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required. A path
            computation server SHOULD implement all types
            of tunnel source address types.
            "

OBJECT      teTunnelSourceAddress
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      teTunnelDestinationAddressType
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      teTunnelDestinationAddress
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathName
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathRowStatus
SYNTAX      RowStatus { active(1) }
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathStorageType
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathType
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathConfiguredRoute
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathBandwidth
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."
```

```
OBJECT      tePathIncludeAny
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathIncludeAll
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathExclude
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathSetupPriority
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHoldPriority
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathProperties
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathAdminStatus
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHopRowStatus
SYNTAX      RowStatus { active(1) }
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHopStorageType
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHopAddrType
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."

OBJECT      tePathHopAddress
MIN-ACCESS  read-only
DESCRIPTION "Write access is not required."
```

```
::= { teModuleCompliance 3 }
```

```
teModuleServerFullCompliance MODULE-COMPLIANCE
```

```
STATUS          current
DESCRIPTION     "When this MIB module is implemented by a path
                computation server with support for read-create,
                then the implementation can claim full
                compliance.
                "

MODULE          -- enclosing module, i.e., TE-MIB
MANDATORY-GROUPS {
    teTrafficEngineeringGroup
}

GROUP          teNotificationGroup
DESCRIPTION     "Implementation of this group is optional."

OBJECT         teAdminGroupRowStatus
SYNTAX         RowStatus { active(1) }
WRITE-SYNTAX   RowStatus { createAndGo(4), destroy(6) }
DESCRIPTION     "Support for notInService, createAndWait, and
                notReady is not required.
                "

OBJECT         teTunnelRowStatus
SYNTAX         RowStatus { active(1), notInService(2) }
WRITE-SYNTAX   RowStatus { active(1), notInService(2),
                          createAndGo(4), destroy(6)
                          }
DESCRIPTION     "Support for createAndWait and notReady is not
                required.
                "

OBJECT         teTunnelSourceAddressType
DESCRIPTION     "Write access is required. An implementation
                of a path computation server SHOULD support all
                types of tunnel source address types.
                "

OBJECT         tePathRowStatus
SYNTAX         RowStatus { active(1), notInService(2) }
WRITE-SYNTAX   RowStatus { active(1), notInService(2),
                          createAndGo(4), destroy(6)
                          }
DESCRIPTION     "Support for createAndWait and notReady is not
                required.
                "

OBJECT         tePathHopRowStatus
```

```
SYNTAX      RowStatus { active(1), notInService(2) }
WRITE-SYNTAX RowStatus { active(1), notInService(2),
                        createAndGo(4), destroy(6)
                        }
DESCRIPTION "Support for createAndWait and notReady is not
            required.
            "
 ::= { teModuleCompliance 4 }
```

END

6. References

6.1. Normative References

- [1] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [2] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Structure of Management Information Version 2 (SMIV2)", STD 58, RFC 2578, April 1999.
- [3] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Textual Conventions for SMIV2", STD 58, RFC 2579, April 1999.
- [4] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Conformance Statements for SMIV2", STD 58, RFC 2580, April 1999.
- [5] Nadeau, T. and J. Cucchiara, "Definitions of Textual Conventions (TCs) for Multiprotocol Label Switching (MPLS) Management", RFC 3811, June 2004.
- [6] Harrington, D., Presuhn, R., and B. Wijnen, "An Architecture for Describing Simple Network Management Protocol (SNMP) Management Frameworks", STD 62, RFC 3411, December 2002.
- [7] Awduche, D., Malcolm, J., Agogbua, J., O'Dell, M., and J. McManus, "Requirements for Traffic Engineering Over MPLS", RFC 2702, September 1999.

6.2. Informative References

- [8] Awduche, D., Berger, L., Gan, D., Li, T., Srinivasan, V., and G. Swallow, "RSVP-TE: Extensions to RSVP for LSP Tunnels", RFC 3209, December 2001.

- [9] Case, J., Mundy, R., Partain, D., and B. Stewart, "Introduction and Applicability Statements for Internet-Standard Management Framework", RFC 3410, December 2002.
- [10] McCloghrie, K. and F. Kastenholz, "The Interfaces Group MIB", RFC 2863, June 2000.
- [11] Thaler, D., "IP Tunnel MIB", RFC 2667, August 1999.
- [12] Jamoussi, B., Andersson, L., Callon, R., Dantu, R., Wu, L., Doolan, P., Worster, T., Feldman, N., Fredette, A., Girish, M., Gray, E., Heinanen, J., Kilty, T., and A. Malis, "Constraint-Based LSP Setup using LDP", RFC 3212, January 2002.

7. Security Considerations

This MIB module relates to the configuration and management of Traffic Engineering tunnels. The unauthorized manipulation of fields in the tables `teAdminGroupTable`, `teTunnelTable`, `tePathTable`, and `tePathHopTable` may lead to tunnel flapping, tunnel paths being changed, or traffic being disrupted. In addition, if these tables are read by unauthorized parties, the information can be used to trace traffic patterns, traffic volumes, and tunnel paths. This may be considered proprietary and confidential information by some providers.

There are a number of management objects defined in this MIB module with a MAX-ACCESS clause of read-write and/or read-create. Such objects may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations. These are the tables and objects and their sensitivity/vulnerability:

`teAdminGroupTable`: Changing this will affect the semantics of include and exclude constraints, and thus traffic takes unintended routes.

`teTunnelTable`: Changing this affects many properties of traffic tunnels.

`tePathTable`: Changing this affects the constraints (including bandwidth) of tunnel paths, as well as the status of the path.

`tePathHopTable`: Changing this affects the route followed by a traffic tunnel path.

Some of the readable objects in this MIB module (i.e., objects with a MAX-ACCESS other than not-accessible) may be considered sensitive or vulnerable in some network environments. It is thus important to control even GET and/or NOTIFY access to these objects and possibly to even encrypt the values of these objects when sending them over the network via SNMP. These are the tables and objects and their sensitivity/vulnerability:

teTunnelTable: Describes tunnel endpoints and traffic volumes.
tePathTable: Describes path properties.
tePathHopTable: Describes path routes.

SNMP versions prior to SNMPv3 did not include adequate security. Even if the network itself is secure (for example by using IPSec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB module.

It is RECOMMENDED that implementers consider the security features as provided by the SNMPv3 framework (see [9], section 8), including full support for the SNMPv3 cryptographic mechanisms (for authentication and privacy).

Further, deployment of SNMP versions prior to SNMPv3 is NOT RECOMMENDED. Instead, it is RECOMMENDED to deploy SNMPv3 and to enable cryptographic security. It is then a customer/operator responsibility to ensure that the SNMP entity giving access to an instance of this MIB module is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

Acknowledgments

It was Tony Li's suggestion that the author embark on this MIB. Many thanks to him and to Der-Hwa Gan for their input and help.

Many thanks, too, to Bert Wijnen for his incredible help, both with improving the correctness, structure, and readability of the MIB module, and with the text of the RFC. Thanks also to Adrian Farrel for his detailed review.

Author's Address

Kireeti Kompella
Juniper Networks, Inc.
1194 N. Mathilda Ave
Sunnyvale, CA 94089

E-Mail: kireeti@juniper.net

Full Copyright Statement

Copyright (C) The Internet Society (2005).

This document is subject to the rights, licenses and restrictions contained in BCP 78, and except as set forth therein, the authors retain all their rights.

This document and the information contained herein are provided on an "AS IS" basis and THE CONTRIBUTOR, THE ORGANIZATION HE/SHE REPRESENTS OR IS SPONSORED BY (IF ANY), THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Intellectual Property

The IETF takes no position regarding the validity or scope of any Intellectual Property Rights or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; nor does it represent that it has made any independent effort to identify any such rights. Information on the IETF's procedures with respect to rights in IETF Documents can be found in BCP 78 and BCP 79.

Copies of IPR disclosures made to the IETF Secretariat and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementers or users of this specification can be obtained from the IETF on-line IPR repository at <http://www.ietf.org/ipr>.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights that may cover technology that may be required to implement this standard. Please address the information to the IETF at ietf-ipr@ietf.org.

Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.